

GILDAS and CLASS

Jérôme PETY (IRAM/Obs. de Paris) on behalf of the IRAM Science Software developers

Mar. 15 - 16 2018, ESO Single Dish Training Workshop 2018

Presentation partly supported by



People (as of 2018 March)

People participating in one way or another

IRAM/Grenoble R. Zylka, J.M. Winters, E. Reynier, V. Pietu, J. Pety, E. Chapillon, A. Castro-Carrizo, M. Bremer, J. Boissier, S. Bardeau.

IRAM/Granada H. Ungerechts, A. Sievers, P. Mellado.

IPAG/Grenoble S. Maret.

LAB/Bordeaux S. Guilloteau.

- Large code contributors: ~ 5.0 FTE/yr
 - R. Zylka MOPSIC.
 - H. Ungerechts PAKO.
 - A. Sievers MIRA + MRTCAL.
 - **E. Reynier** kernel + OMS.
 - V. Pietu CLIC + RDI.
 - **J.** Pety kernel + MRTCAL + CLASS + MAPPING.
 - P. Mellado TAPAS.
 - **A.** Castro-Carrizo CLIC pipeline + OBS.
 - J. Boissier ASTRO.
 - **S. Bardeau** kernel (including the python binding) + CLASS + MRTCAL.
 - S. Maret CLASS/WEEDS.
 - **S. Guilloteau** Kernel + MAPPING.



Scope: I. Science Software at IRAM


Many different kinds of software at IRAM

- 1. Proposal (submission, TAC, statistics, ...)
- 2. Preparation of observations, e.g. setups.
- 3. Scheduling and monitoring of observed projects (dynamic scheduling, pool observing).
- 4. Data acquisition:
 - 4.1 Low level, e.g. hardware control (antennas, receivers, correlators, etc...)
 - 4.2 High level, e.g. operator and observer interface.
- 5. Data archiving.
- 6. Data reduction and analysis (single dish + interferometry).
- 7. Generic plot package.

Science software deals only with a subset Points: 1, 2, 3, 4.2, 6, and 7. GILDAS deals with an even smaller subset Points: 2, 4.2, 6 and 7.

Scope: III. GILDAS at IRAM 450 000 executable lines

- Common facilities
 - Command line interpreter: SIC;
 - Graphical possibilities: GREG
 (1D: curves, 2D: images, 3D: spectra cubes).
 - Preparation of observations: ASTRO.
- 30m
 - Spectroscopy: TELCAL + MRTCAL + CLASS.
- NOEMA
 - Calibration: CLIC;
 - Imaging + Deconvolution: MAPPING.



GILDAS Strengths

Large range of supported systems Linux, Mac/OSX, (Windows).
Light weight Data reduction and analysis possible on laptops.
35 years of history ⇒ Accumulated expertise.

GILDAS users


- IRAM AODs: Instrument monitoring, data pipelining.
- IRAM users: Data reduction.
- Other facilities users
 - CLASS is used in many facilities (e.g., Herschel/HIFI, SOFIA/UpGREAT, APEX, NAN-TEN2, 40m, GBT, Effelsberg, PMO/Kosma, ...).
 - Science analysis, and publication quality figures.
- All kind of public from beginners to data specialists.
 - Easyness of use for new users.
 - Flexibility for data specialists.
- ⇒ GILDAS evolutions must be thought with all users in mind.

User support:

I. Documentation


Web page http://www.iram.fr/IRAMFR/GILDAS.

Mail to gildas@iram.fr.




User support:


II. Web page http://www.iram.fr/IRAMFR/GILDAS



User support:

III. answers to gildas@iram.fr





- Total number of threads: 161/year.
- Number of emails per threads: 4.4.
- Median time to
 - First answer: 6h;
 - Final answer: 25h.

Bug report: I. Wrong way

Hi,

I have just stumbled on an obnoxious bug which prevents me from making the discovery of the century. I will defend my PhD thesis tomorrow. Fix this bug in the coming minutes.

Toto.

Bug report: II. Right way

Dear Gildas team,

Your software is great. For the first time in my life, I encountered a segmentation fault using it. I succeeded to reproduce the bug with a simple list of commands. I attach the following information: version of gildas I am currently using, list of commands and the data set to reproduce the bug. I hope this will help you solve the bug in the coming months. Continue the great work.

Best regards, Toto.

gildas version: mar18b (x86_64-redhat6.4-ifort) source tree

List of commands: LAS90> file in test LAS90> find Blablablabla... Segmentation fault

Data set attached: test.30m

No software is the answer to all these:

- Best (i.e. most recent) computing technology.
- Best portability.
- Best speed.
- Best ease of use (CLI and GUI).
- Best (i.e. shortest) learning curve.
- Best functionalities.
 - Best data calibration methods.
 - Best data mapping methods.
 - Best (i.e. most complete) analysis methods.
 - Best graphical possibilities.
- Best cost.

IRAM Science Software Strategy

Maintain high-quality software for IRAM instruments while staying open to outside world

- Focused but generic developments;
- In/out fillers;
- Python binding.

"Short", "focused" development cycles

- No one-fit-all-use-cases-in-astronomy software.
- Ruptures are possible but exceptional (e.g., data formats) and foresee large timescale for users to adapt.

A good balance between software astronomers and software engineers

- In-house astronomers make the link between the community and the engineers.
- Keeping a science activity is the best way to understand the community needs on a daily basis.
- Prototypes are useful first steps for more professional developments (e.g., IPP \Rightarrow PMS, Weeds \Rightarrow linedb).


Continuous aggregation of functionality without creating black boxes


- Integration of functionality enable to simplify the interaction with ever increasing data complexity.
- Viewing the intermediate processing steps enable to keep control of the data reduction.

Professionalization

- Prototypes are rewritten to get a better design and an easier medium to long term maintenance.
- Yearly versions for the online acquisition.
- Major developments made in branches (GREG2011) or plug-ins (WEEDS) to avoid disruption.
- Much testing done before releasing new developments (GREG2011, CLIC pipeline, MRTCAL, ...).


Need generic help? I. Browsing the widgets






GILDAS was upgraded to accompany the change of name of the IRAM interferometer from


Web pages opened in your web browser




Need generic help? II. Demonstration procedures


Online HELP displayed in the terminal window







Demonstration executed in the terminal and/or the plotting window



Need CLASS help?

```
GILDAS web page http://www.iram.fr/IRAMFR/GILDAS/
```

CLASS documentations and cookbooks Widget>Help>Class>...

Online help

```
LAS> HELP ! Summary of all commands, gathered by language
. . .
LAS\
  ACCUMULATE ASSOCIATE
                            AVERAGE
                                         BASE
                                                      BOX
                                                                   CATALOG
  CONSISTENCY COPY
                            DROP
                                        DUMP
                                                     EXTRACT
                                                                   FILE
LAS> HELP LAS\ ! (with backslash) Language help with short command description
     LAS\ Command Language Summary
                  Add R and T observation.
ACCUMULATE
ASSOCIATE
                  Add an Associated Array to the R observation
AVERAGE
                  Average all the observations of the current index.
LAS> help average ! Command help
    LAS\AVERAGE [/RESAMPLE [NX Xref Xval
                                                               [/NOCHECK
                                              Xinc
                                                     Unitll
[SOURCE|POSITION|LINE|SPECTROSCOPY|CALIBRATION]]
Average all the spectra of the current index using the current weighting
function (see SET WEIGHT).
LAS> help average /resample ! Command subtopic help
. . .
```

Helpdesk (Questions? Comments? Bug reports?): gildas@iram.fr

```
LAS> file in demo
LAS> find
LAS> list
Current index contains:
 N;V
      Source
                                 Telescope
                                               Lambda
                                                           Beta Sys Sca Sub
                    Line
. . .
8600;4 B0355+508
                    12CO(1-0)
                                                          +60.0 Eq
                                                                   9682.
                                 30M-V02-B100
                                                 +65.2
8601;4 B0355+508
                    12CO(1-0)
                                 30M-V02-B100
                                                 +68.2
                                                          +60.0 Eq
                                                                   9682.
8602;4 B0355+508
                    12CO(1-0)
                                 30M-V02-B100
                                                 +71.3
                                                          +60.0 Eq 9682.
8603;4
       B0355+508
                    12CO(1-0)
                                 30M-V02-B100
                                                 +74.4
                                                          +60.0 Eq 9682.
                                 30M-V02-B100
8604;4
       B0355+508
                    12CO(1-0)
                                                 +77.4
                                                          +60.0 Eq 9682.
8605;4
       B0355+508
                    12CO(1-0)
                                 30M-V02-B100
                                                 +80.5
                                                          +60.0 Eq 9682.
8606;4
       B0355+508
                    12CO(1-0)
                                                 +83.5
                                                          +60.0 Eq 9682.
                                 30M-V02-B100
8607;4
                    12CO(1-0)
                                                 +86.6
                                                                   9682.
       B0355+508
                                 30M-V02-B100
                                                          +60.0 Eq
8608;4
                    12CO(1-0)
                                                 +89.7
                                                                   9682.
       B0355+508
                                 30M-V02-B100
                                                          +60.0 Eq
8609;4
       B0355+508
                    12CO(1-0)
                                 30M-V02-B100
                                                 +92.7
                                                          +60.0 Eq
                                                                   9682.
                                                                   9682.
8610;4
       B0355+508
                    12CO(1-0)
                                 30M-V02-B100
                                                 +95.8
                                                          +60.0 Eq
                                 30M-V02-B100
8611;4
       B0355+508
                    12CO(1-0)
                                                 +98.8
                                                          +60.0 Eq
                                                                   9682.
8612;4
       B0355+508
                    12CO(1-0)
                                                +101.9
                                                          +60.0 Eq
                                                                   9682.
                                 30M-V02-B100
8613;4
       B0355+508
                    12CO(1-0)
                                 30M-V02-B100
                                                +104.9
                                                          +60.0 Eq
                                                                    9682.
8614;4
       B0355+508
                    12CO(1-0)
                                 30M-V02-B100
                                                +108.0
                                                          +60.0 Eq
                                                                   9682.
LAS>
```

 \Rightarrow Too many information.

```
LAS> list /scan
. . .
 B0355+508
               12CO(1-0)
                            30M-V02-B100
                                              -108.5:
                                                         +108.8
                                                                           +70.0
                                                                                            9626
                                                                                                   73
                                                                                        Eq
                                                                           +80.0
                                                                                            9627
 B0355+508
               12CO(1-0)
                            30M-V01-A100
                                              -108.5:
                                                         +108.8
                                                                                        Eq
                                                                                                   73
               12CO(1-0)
                                              -108.5:
                                                                           +80.0
                                                                                            9627
                                                                                                   73
 B0355+508
                            30M-V02-B100
                                                         +108.8
                                                                                        Eq
 B0355+508
               12CO(1-0)
                                              -109.4:
                                                                           +90.0
                                                                                        Eq
                                                                                            9628
                                                                                                   73
                            30M-V01-A100
                                                         +107.9
               12CO(1-0)
                                                                           +90.0
                                                                                            9628
                                                                                                   73
 B0355+508
                            30M-V02-B100
                                              -109.4:
                                                         +107.9
                                                                                        Eq
 B0355+508
               12CO(1-0)
                            30M-V01-A100
                                              -109.6:
                                                         +107.7
                                                                          +100.0
                                                                                        Eq
                                                                                            9629
                                                                                                   73
 B0355+508
               12CO(1-0)
                            30M-V02-B100
                                              -109.6:
                                                                          +100.0
                                                                                            9629
                                                                                                    73
                                                                                        Eq
                                                         +107.7
               12CO(1-0)
                                                                                +108.0 Eq
                                                                                            9634
                                                                                                   73
 B0355+508
                            30M-V01-A100
                                                                      -109.3:
                                                   -100.0
 B0355+508
               12CO(1-0)
                            30M-V02-B100
                                                   -100.0
                                                                      -109.3:
                                                                                +108.0 Eq
                                                                                            9634
                                                                                                    73
 B0355+508
               12CO(1-0)
                            30M-V01-A100
                                                    -90.0
                                                                      -109.4:
                                                                                +107.9 Eq
                                                                                            9635
                                                                                                    73
               12CO(1-0)
                                                    -90.0
                                                                                +107.9 Eq
                                                                                            9635
                                                                                                    73
 B0355+508
                            30M-V02-B100
                                                                      -109.4:
               12CO(1-0)
                                                    -80.0
                                                                                +107.8 Eq
                                                                                            9636
                                                                                                   73
 B0355+508
                            30M-V01-A100
                                                                      -109.5:
               12CO(1-0)
                                                    -80.0
                                                                                +107.8 Eq
 B0355+508
                            30M-V02-B100
                                                                      -109.5:
                                                                                            9636
                                                                                                   73
 B0355+508
               12CO(1-0)
                            30M-V01-A100
                                                    -70.0
                                                                      -109.2:
                                                                                +108.1 Eq
                                                                                            9637
                                                                                                   73
. . .
LAS>
```

⇒ One line per scan and front-end/back-end combination

```
LAS> list /scan /brief
Current index contains:
 9608: 146
             9609: 146
                         9610: 146
                                      9611: 146
                                                  9612: 146
                                                               9613: 146
 9614: 146
             9615: 146
                                      9617: 146
                                                  9619: 146
                                                               9620: 146
                         9616: 146
 9621: 146
             9622: 146
                         9623: 146
                                      9624: 146
                                                  9625: 146
                                                               9626: 146
 9627: 146
             9628: 146
                         9629: 146
                                      9634: 146
                                                  9635: 146
                                                               9636: 146
 9637: 146
             9638: 146
                         9639: 146
                                      9640: 146
                                                  9641: 146
                                                               9642: 146
 9643: 146
             9645: 146
                         9646: 146
                                      9647: 146
                                                  9648: 146
                                                               9649: 146
 9650: 146
             9651: 146
                         9652: 146
                                      9653: 146
                                                  9654: 146
                                                               9655: 146
 9665: 146
             9666: 146
                         9667: 146
                                      9668: 146
                                                  9669: 146
                                                               9670: 146
 9671: 146
             9672: 146
                         9673: 146
                                      9674: 146
                                                  9676: 146
                                                               9677: 146
 9678: 146
             9679: 146
                         9680: 146
                                      9681: 146
                                                  9682: 146
LAS>
```

 \Rightarrow Just the list of scans and the number of dumps per scan.

```
LAS> list /toc
equivalent to
LAS> list /toc source line telescope
Current index contains:
Number of sources..... 1
              8614 (100.0%)
   B0355+508
Number of lines..... 1
             8614 (100.0%)
   12CO(1-0)
Number of backends.....
   30M-V01-A100
               4307 ( 50.0%)
   30M-V02-B100
               4307 ( 50.0%)
Number of setups.....
   B0355+508 12CO(1-0)
                                           4307 (50.0%)
                          30M-V01-A100
   B0355+508 12CO(1-0) 30M-V02-B100
                                           4307 (50.0%)
LAS>
```

 \Rightarrow Default table of contents.

```
LAS> list /toc observed scan
Number of observation dates
    12-SEP-2005
                      8614 (100.0%)
Number of scans.....
                       59
            9608
                        146 ( 1.7%)
            9609
                        146 ( 1.7%)
            9610
                        146 ( 1.7%)
            9611
                        146 ( 1.7%)
            9612
                        146 ( 1.7%)
            9613
                        146 ( 1.7%)
            9614
                        146 ( 1.7%)
Number of setups.....
                         59
    12-SEP-2005
                                    146 ( 1.7%)
                        9608
    12-SEP-2005
                        9609
                                    146 ( 1.7%)
    12-SEP-2005
                        9610
                                    146 ( 1.7%)
    12-SEP-2005
                        9611
                                    146 ( 1.7%)
    12-SEP-2005
                        9612
                                    146 ( 1.7%)
    12-SEP-2005
                        9613
                                    146 ( 1.7%)
                                    146 ( 1.7%)
    12-SEP-2005
                        9614
LAS>
```

⇒ Customized table of content.